Configuration de la fonctionnalité de mise en file d'attente native CUCM

Contenu

Introduction Conditions préalables Conditions requises Components Used Informations générales Configuration Vérification État de la file Compteurs de service Dépannage

Introduction

Ce document décrit comment configurer la fonctionnalité de mise en file d'attente native des appels de Cisco Unified Communications Manager (CUCM).

Conditions préalables

Conditions requises

Cisco vous recommande de prendre connaissance des rubriques suivantes :

- CUCM 9 et versions ultérieures
- Fonction de recherche d'appel de base

Components Used

Les informations contenues dans ce document sont basées sur CUCM 11.X et les versions ultérieures.

The information in this document was created from the devices in a specific lab environment. All of the devices used in this document started with a cleared (default) configuration. If your network is live, make sure that you understand the potential impact of any command.

Informations générales

Pour CUCM, son pilote de recherche a souvent plus d'appels que son membre de recherche ne peut en traiter à un moment donné. La fonctionnalité de mise en file d'attente native de CUCM permet de mettre en file d'attente les appelants pilotes de recherche pendant qu'ils attendent

Note: La fonction de mise en file d'attente native permet de mettre en file d'attente jusqu'à 100 appelants par pilote de recherche.

Configuration

Étape 1. Accédez à Media resources > Music on Hold Source Page, comme indiqué dans l'image



his product contains cryptographic features and is subject to United States and local country laws governing import, export, transfer and use. Delivery of Cisco cryptographic for comply with applicable laws and regulations. If you are upable to comply

Étape 2. Créez une nouvelle source audio, comme illustré dans l'image :

Cisco Unified CM Administration For Cisco Unified Communications Solutions	
System 👻 Call Routing 👻 Media Resources 👻 Advanced Features 👻 Device 👻 Application 👻 User Management 👻 Bulk Administration 👻 Help 👻	
Find and List Music On Hold Server Audio Sources	
🕂 Add New 🏢 Select All 📰 Clear All 💥 Delete Selected	
- Status - i 3 records found	
Music On Hold Server Audio Source (1 - 3 of 3)	
Find Music On Hold Server Audio Source where MOH Audio Stream Number 🗸 begins with 🔪 🛛 Find Clear Filter 🕹	
MOH Audio Stream Number *	
	SampleAudioSource
□ <u>2</u>	ToneOnHold
r 2	QueueAudioSource
Add New Select All Clear All Delete Selected	

Étape 3. Réglez la multidiffusion sur le paramètre souhaité et définissez les paramètres d'annonce, comme illustré dans l'image :

System - Call Routing - Media R	Resources 👻 Advanced Features 👻 Devic	e 👻 Application 👻 User Management 👻	Bulk Administration 👻 Help 👻
Music On Hold Audio Source	Configuration		
🔚 Save 🗶 Delete 🕂 Add 1	New Dipload File		
Shahara			
Status: Ready			
Music On Hold Server Audio	Source Information		
MOH Audio Source File San	npleAudioSource	-	
MOH Audio Source Name* Que	eueAudioSource		
Allow Multi-casting			
ErrorCode: 0 ErrorText: Translation Complete DurationSeconds: 338 DiskSpaceKB: 8092 Law DateTime: 1130860118 HighDateTime: 0 OutputFileList: SampleAudioSource.alaw.wav SampleAudioSource.alaw.wav SampleAudioSource.alaw.wav			
Announcement Settings			
Initial Announcement	Welcome Greeting Sample	View Details	
Initial Announcement Played	Always	•	
Periodic Announcement Interval*	88	(10 - 300 seconds)	
Locale Announcement*	English United States	(10 - 500 Seconds)	
1			

Étape 4. Sélectionnez l'annonce initiale, comme illustré dans l'image :

— Announcement Settings ——			
Initial Announcement	Welcome Greeting Sample	•	View Details
Initial Announcement Played*	Always	•	
Periodic Announcement	Wait In Queue Sample	•	View Details
Periodic Announcement Interval*	30		(10 - 300 seconds)
Locale Announcement*	English United States	-	

Étape 5. Sélectionnez l'annonce périodique, comme illustré dans l'image :

- Announcement Settings Initial Announcement	Welcome Greeting Sample	•	View Details
Initial Announcement Played*	Always	-	
Periodic Announcement	Wait In Queue Sample	•	View Details
Periodic Announcement Interval*	30		(10 - 300 seconds)
Locale Announcement*	English United States	-	

Étape 6. Sélectionnez l'intervalle d'annonce périodique (la valeur par défaut est 30 secondes), comme indiqué dans l'image :

Announcement Settings ——			
Initial Announcement	Welcome Greeting Sample	•	View Details
Initial Announcement Played*	Only for queued calls	•	
Periodic Announcement	Wait In Queue Sample	•	View Details
Periodic Announcement Interval*	30		(10 - 300 seconds)
Locale Announcement*	English United States	•	

Étape 7 : Sélectionnez les paramètres régionaux des annonces, comme indiqué dans l'image :

Announcement Settings ——			
Initial Announcement	Welcome Greeting Sample	•	View Details
Initial Announcement Played*	Only for queued calls	•	
Periodic Announcement	Wait In Queue Sample	-	View Details
Periodic Announcement Interval*	30		(10 - 300 seconds)
Locale Announcement*	English United States	-	

Pendant que l'appelant est dans la file d'attente, il reçoit un traitement d'attente musicale qui dépend des paramètres d'attente musicale du réseau pour ce pilote de recherche. Il y a une option (Page source audio Musique d'attente et le champ est Lecture de l'annonce initiale) pour lire d'abord l'annonce initiale, puis proposer un appel au pilote de recherche. Si aucun agent ne répond à l'appel, il place l'appelant en attente (dans la file d'attente) et, en cas de succès, il répète l'annonce (fournie périodiquement) et la musique en attente.

Announcement Settings for Held and Hunt Pilot Calls-		
Initial Announcement	Welcome Greeting Sample	View Details
Initial Announcement for queuing-enabled Hunt Pilot cals*	Play announcement before routing to Hunt Member	•
Periodic Announcement	Wait In Queue Sample	View Details
Periodic Announcement Interval*	30	(10 - 300 seconds)
Locale Announcement*	English, United States	-

La deuxième option consiste à proposer d'abord l'appel pour rechercher le numéro d'annuaire pilote (DN) et, si l'appel n'est pas pris, il place l'appelant en attente (dans la file d'attente) et, en cas de succès, fournit une annonce initiale, une annonce répétée (fournie périodiquement) et de la musique en attente.

Announcement Settings for Held and Hunt Pilot Calls						
Initial Announcement	Welcome Greeting Sample	View Details				
Initial Announcement for queuing-enabled Hunt Pilot calls	* Play announcement if call is queued	•				
Periodic Announcement	Wait In Queue Sample	View Details				
Periodic Announcement Interval*	30	(10 - 300 seconds)				
Locale Announcement*	English, United States					

Étape 8. Dans la page de configuration, accédez à Call Routing > Route/Hunt > Hunt Pilot, comme indiqué dans l'image :

88 -	alala asso Cisco Ur	nified CM Cor	ns 🤉	C asia Secu	ure Login P	age	
cisco	Cisco Unified CM Administration For Cisco Unified Communications Solutions						
System 👻	Call Routing 👻	Media Resources	- A0	vanced Features	 Device 	Application	- Us
	AAR Group						
	Dial Rules		•				
Cisc	Route Filter			tration)		_
Systen	Route/Hunt		•	Route Gro	up		
	SIP Route P	attern		Route List			
Systen	Class of Co	ntrol	•	Route Patt	tern		s.
Please	Intercom		•				
VMwar	Cilent Matte	r Codes		Line Group	p		k 1: 8
	Forced Auth	orization Codes		HUN LIST			
Last Succes	Translation	Pattern	(Hunt Pilot			
Copyright @	Call Park				\nearrow		
All rights re:	Directed Ca	ll Park					
This produc	Call Pickup	Group		bject to Unit	ed States and	local country	laws g

Étape 9. Une liste de recherche doit être définie et sélectionnée, comme illustré dans l'image :

Hunt Pilot Configuration					
Save					
Status Status: Ready					
Pattern Definition-					
Hunt Pilot*	7777		7		
Route Partition	< None >	-			
Description					
Numbering Plan	< None >	~			
Route Filter	< None >	~			
MLPP Precedence*	Default	•			
Hunt List*	Test_Native_Call_Queue	•	(<u>Edit</u>)		

Étape 10. Sélectionnez Queue Calls sur la page Hunt Pilot pour activer la mise en file d'attente pour ce pilote de recherche, comme illustré dans l'image :

Network Hold MOH Source & Announcements	QueueAudioSource	View Details
Maximum Number of Callers Allowed in Queue*	32	(1-100)
When Queue is full:		
Disconnect the call		
C Route the call to this destination		
Full Queue Calling Search Space	< None >	-
Maximum Wait Time in Queue*	900	(10 - 3600 second
When maximum wait time is met:		
Disconnect the call		
$^{\odot}$ Route the call to this destination		
Maximum Wait Time Calling Search Space	< None >	-
When no hunt members are logged in or registered:		
Disconnect the call		
Route the call to this destination		
No hunt members logged in or registered Calling Sear	rch Space < None >	_

Le nombre maximal d'appelants simultanés dans la file d'attente pour chaque pilote de recherche peut être configuré de 1 à 100 (valeur par défaut : 32)

Le temps d'attente maximal dans la file d'attente pour chaque pilote de recherche peut être configuré entre 0 et 3 600 (valeur par défaut : 900)

Pour chaque pilote de recherche, les appelants peuvent être acheminés vers des destinations secondaires configurables si :

- L'attente de file d'attente maximale est atteinte
- La capacité maximale de la file d'attente a été atteinte
- Aucun agent n'est connecté ou enregistré

Étape 11. Sélectionnez une source audio pour l'attente musicale et les annonces, comme indiqué dans l'image :

Network Hold MOH Source & Announcements	QueueAudioSource	 View Details
Maximum Number of Callers Allowed in Queue*	32	(1-100)
When Queue is full:		
Ø Disconnect the call		
Route the call to this destination		
Full Queue Calling Search Space	< None >	-
Maximum Wait Time in Queue*	900	(10 - 3600 seconds
When maximum wait time is met:		
Ø Disconnect the call		
Route the call to this destination		
Maximum Wait Time Calling Search Space	< None >	-
When no hunt members are logged in or registered:		
Ø Disconnect the call		
Route the call to this destination		
No hunt members logged in or registered Calling Search	ch Space < None >	-

Étape 12. Définissez le nombre maximal d'appelants et le temps d'attente maximal de la file d'attente, comme indiqué dans l'image :

✓ Queue Calls			
Network Hold MOH Source & Announcements	QueueAudioSource	View Details	
Maximum Number of Callers Allowed in Queue*	32	(1-100)	Default=32
When Queue is full:			
Ø Disconnect the call			
Route the call to this destination			
Full Queue Calling Search Space	< None >	-	
Maximum Wait Time in Queue*	900	(10 - 3600 seconds)	Default=900
When maximum wait time is met:			
Ø Disconnect the call			
® Route the call to this destination			
Maximum Wait Time Calling Search Space	< None >	-	
When no hunt members are logged in or registered:			
Ø Disconnect the call			
® Route the call to this destination			
No hunt members logged in or registered Calling Search Space	< None >	-	

Étape 13. Enfin, configurez le routage secondaire si nécessaire, comme illustré dans l'image :

Queue Calls		
Network Hold MOH Source & Announcements	QueueAudioSource	View Details
Maximum Number of Callers Allowed in Queue*	32	(1-100)
When Queue is full:		
C Disconnect the call		
Route the call to this destination Full Queue Calling Search Space	9725551212	
	testCSS	•
Maximum Wait Time in Queue*	900	(10 - 3600 seconds)
When maximum wait time is met:		
C Disconnect the call		
Route the call to this destination Maximum Wait Time Calling Search Space	9725551313	
	testCSS	•
When no hunt members are logged in or registered:		
C Disconnect the call		
Route the call to this destination No hunt members logged in or registered Calling Search	9725551414	
	rch Space testCSS	

Vérification

État de la file

Vous pouvez configurer un nouveau modèle de bouton de téléphone dont l'option **État de la file d'attente** est configurée sur n'importe quelle ligne du téléphone. Vous devez appliquer le modèle de bouton de téléphone sur le téléphone correspondant, comme illustré dans l'image :

Phone Button Template Configuration		
🔚 Save 🗶 Delete 📔 Copy 蠀 Reset 🧷 Apply Config 🕂 Add New		
Status Update successful		
Phone Button Template Information Button Template Name * Standard 7965 SCCP - Native		
Button Information		
Button	Feature	
1	Line **	
2	Hunt Group Logout	
3	Queue Status	

Une fois que le modèle de bouton de téléphone est attribué au téléphone, vous pouvez voir **État de la file d'attente** sur la ligne, comme illustré dans l'image,

21:37 01/18/12



Les statistiques de file d'attente sont affichées, comme illustré dans l'image :



Compteurs de service

De nouveaux compteurs de facilité de maintenance sont ajoutés dans l'outil de surveillance en temps réel (RTMT) sous **Cisco Hunt Pilots** à la mise en file d'attente de surveillance.



Dépannage

Il n'existe actuellement aucune information de dépannage spécifique pour cette configuration.