



User-Based Firewall Support

Firewalls traditionally apply rules based on source and destination IP addresses. In the new, highly dynamic mobile world, IP addresses of end systems constantly change. Therefore it becomes increasingly difficult to have a particular user group function assigned to a particular block of IP addresses. It is also difficult to apply firewall policies for a user group that is the source of the traffic. This feature allows source IP addresses to be associated with user groups. Network administrators can apply firewall policies based on user-groups, and the infrastructure can seamlessly apply these security policies.

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information for User-Based Firewall Support section.

Use Cisco Feature Navigator to find information about platform support and Cisco IOS and Catalyst OS software image support. To access Cisco Feature Navigator, go to <http://www.cisco.com/go/cfn>. An account on Cisco.com is not required.

- [Finding Feature Information, page 1](#)
- [Prerequisites for User-Based Firewall Support, page 2](#)
- [Restrictions for User-Based Firewall Support, page 2](#)
- [Information About User-Based Firewall Support, page 2](#)
- [How to Configure User-Based Firewall Support, page 5](#)
- [Configuration Examples for User-Based Firewall Support, page 29](#)
- [Additional References, page 30](#)
- [Feature Information for User-Based Firewall Support, page 31](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest caveats and feature information, see [Bug Search Tool](#) and the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the feature information table.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Prerequisites for User-Based Firewall Support

Hardware Requirements

- Access Control Server
- Cisco Network Access Device, which can be any of the following:
 - Cisco 7200 router
 - Cisco 1800 router
 - Cisco 2800 router
 - Cisco 3800 router

Software Requirements

- Cisco IOS Release 12.4(20)T or a later release
- An Ingress Security feature that uses the Identity Policy infrastructure for policy application

Restrictions for User-Based Firewall Support

User-group mapping is based on the IPv4 address of the end-host's source. The "user-group" match criterion is supported for inspect class-maps.

Authentication Proxy and IP Admission

Authentication Proxy and IP Admission is an input-only feature that should be configured on all the interfaces of the source zone. The Authentication Proxy and IP Admission feature is not virtual routing and forwarding (VRF)-aware; therefore, the user-group Zone Policy Firewall policies cannot be applied on a per VRF basis.

Information About User-Based Firewall Support

Feature Design of User-Based Firewall Support

The User-Based Firewall Support feature was designed to provide identity or user-group based security that provides differentiated access for different classes of users. Classification can be provided on the basis of user identity, device type (for example, IP phones), location (for example, building) and role (for example, engineer). Because of the dynamic nature of end-host access, where every user is different and the resource he or she

accesses is different, it is important to associate end-user's identity, role, or location with security policies. This association prevents the need for administrators to constantly update policy filters, a cumbersome task. The end-user identity can be derived through a variety of different mechanisms. Once a user's identity is established, security policies will be aware of the user's identity, not just the source address. Individual policies can be enforced allowing for greater control.

Cisco IOS supports several features that offer dynamic, per-user authentication and authorization of network access connections. These features include 802.1X, IKE, Authentication Proxy, Network Admission Control (NAC), and so on. These features allow network administrators to enforce security policies on per-user basis. By integrating authentication features with Cisco Policy Language-based features such as Zone Based Firewall, quality of service (QoS), and so on, the combination can provide a transparent, reliable, ease to manage and deploy security solution to dynamically authenticate and enforce policies on a per user basis.

Cisco IOS User-Based Firewall Support leverages existing authentication and validation methods to associate each source IP address to a user-group. User-group association can be achieved using two methods. The first method (Tag and Template) uses locally defined policies to achieve the association, while the second method obtains the user-group information from the access control server (ACS) and requires no further configuration on the network access device (NAD).

The User-Based Firewall Support feature leverages the Tag and Template concept where the authenticating server returns a tag-name on validating the user credentials. This tag received on the authentication device is mapped to a template. The template is a control plane policy map that refers to an identity policy configured on the device. The identity policy contains the access policies that are to be applied for the corresponding tag-name. The identity policy defines one or more user-groups to which the source IP would be associated. This mapping provides administrators with flexibility to associate the end-host with multiple user-group memberships. The scope of the user-group defined in the identity policy is local to the device. Once the end-host's user-group membership has been established, other Cisco IOS policy language based features can enforce security policies on a per user-group basis.

Match Criterion

The match user-group criterion in the inspect type class map configuration can be used to enforce security policies on a per user-group basis. The match criterion filters the traffic stream based on the client's source IP address in the specified user-group, making it independent of the authentication method that established the group membership. The match criterion in the inspect type class map enables inspection for any ingress traffic and for any protocol, thereby enabling inspection for all traffic.

Firewall Support

Cisco IOS Firewall includes multiple security features. Cisco IOS Firewall stateful packet inspection provides true firewall capabilities to protect networks against unauthorized traffic and control legitimate business-critical data. Authentication proxy controls access to hosts or networks based on user credentials stored in an authentication, authorization, and accounting (AAA) server. Multi-VRF firewall offers firewall services on virtual routers with VRF, accommodating overlapping address space to provide multiple isolated private route spaces with a full range of security services. Transparent firewall adds stateful inspection without time-consuming, disruptive IP addressing modifications. Application inspection controls application activity to provide granular policy enforcement of application usage, protecting legitimate application protocols from rogue applications and malicious activity. For more information on firewall support see the [Cisco IOS Firewall Design Guide](#).

Authentication Proxy

The Cisco IOS Firewall Authentication Proxy feature provides dynamic, per-user authentication and authorization, authenticating users against industry standard TACACS+ and RADIUS authentication protocols. Authenticating and authorizing connections by users provides more robust protection against network attacks. See the Authentication Proxy document for more information about this feature.

Zone-Based Policy Firewall

Cisco IOS Zone-Based Policy Firewall can be used to deploy security policies by assigning interfaces to different zones and configuring a policy to inspect the traffic moving between these zones. The policy specifies a set of actions to be applied on the defined traffic class. For more information see the document Zone-Based Firewall.

Tag and Template

The Tag and Template feature allows network administrators to define enforcement policies on a local device and have a RADIUS server specify the policy selector to be enforced. This feature can be applied to a NAC architecture. See the Tag and Template feature guide for more information about this feature.

Network Admission Control

In a typical Network Admission Control deployment, an ACS or a RADIUS server is used for validating the user posture information and for applying the policies on the NAD. A centralized ACS can be used to support multiple NADs. This solution has inherent problems associated with it, namely:

- Version control of policies. Typically, a specific NAD that is running a Cisco IOS image may support some access control lists (ACLs), and another NAD may support a different version. Managing different versions can be a problem.
- Users connect on different interfaces to the NAD, and on the basis of the interface type, the policies that can be applied to the user can change, and the NAD can determine the policies to be applied. In the current architecture, the ACS sends the same set of policies to all the NADs when a profile is matched, which does not give enough control to the administrator to configure the policies on the basis of the NAD configuration.

Configuring the Tag and Template feature allows the ACS to map users to specific groups and associate a tag with them. For example, the Usergroup1 user group may have a tag with the name usergroup1. When the NAD queries the ACS for the policies, the ACS can return the tag that is associated with the user group. When this tag is received at the NAD, the NAD can map the tag to a specific template that can have a set of policies that are associated with the user group. This mapping provides administrators with the flexibility to configure the template on a NAD basis, and the policies can change from NAD to NAD even though the tag is the same.

In summary, a template must be configured on the NAD, and the template must be associated with a tag. When the ACS sends the policies back to the NAD, the template that matches the tag that was received from the ACS is used.

Access Control List Overview

Cisco provides basic traffic filtering capabilities with access control lists (also referred to as access lists). Access lists can be configured for all routed network protocols (IP, AppleTalk, and so on) to filter the packets of those protocols as the packets pass through a router. You can configure access lists at your router to control access to a network. Access lists can prevent certain traffic from entering or exiting a network.

How to Configure User-Based Firewall Support

Configuring Access Control Lists

To configure ACLs, perform the steps in this section. Policy specific ACLs are defined under the identity policy.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **ip access-list extended** *access-list-name*
4. **permit** *protocol* **any** **host** *ip-address*
5. **end**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2	configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3	ip access-list extended <i>access-list-name</i> Example: Router(config)# ip access-list extended auth_proxy_acl	Defines an IP access list and enters extended named access list configuration mode.

	Command or Action	Purpose
Step 4	permit <i>protocol</i> any host <i>ip-address</i> Example: <pre>Router(config-ext-nacl)# permit tcp any host 192.168.104.136</pre>	Sets the permission for an access list using TCP.
Step 5	end Example: <pre>Router(config-ext-nacl)# end</pre>	Exits extended named access list configuration mode.

Configuring the Identity Policy for Tag and Template

To configure the identity policy for Tag and Template, perform the steps in this section. Usergroup support is achieved by configuring the usergroup that is to be associated with the IP address on the NAD itself using a locally defined identity policy. A tag is received from the ACS that matches a template (identity policy) on the NAD. The user-group associated with the IP address is obtained from the NAD.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **identity policy** *policy-name*
4. **user-group** *group-name*
5. **access-group** *group-name*
6. **end**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: <pre>Router> enable</pre>	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2	configure terminal Example: <pre>Router# configure terminal</pre>	Enters global configuration mode.

	Command or Action	Purpose
Step 3	identity policy <i>policy-name</i> Example: Router(config)# identity policy auth_proxy_ip	Creates an identity policy and enters identity policy configuration mode.
Step 4	user-group <i>group-name</i> Example: Router(config-identity-policy)# user-group auth_proxy_ug	Establishes a user-group.
Step 5	access-group <i>group-name</i> Example: Router(config-identity-policy)# access-group auth_proxy_acl	Specifies the access-group to be applied to the identity policy.
Step 6	end Example: Router(config-identity-policy)# end	Exits identity policy configuration mode.

Configuring Control Type Tag Class-Maps or Policy-Maps for Tag and Template

To configure control type tag class-maps or policy-maps for Tag and Template, perform the steps in this section. Tag names are received from the AAA server as authorization data and are matched with their respective class-maps. The security policies that are associated with the identity policies are applied to the host. In this way host IP addresses gain membership of user-groups.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **policy-map type control tag** *policy-map-name*
4. **class type control tag** *control-class-name*
5. **identity policy** *policy-name*
6. **exit**
7. **configure terminal**
8. **class-map type control tag match-all** *class-map-name*
9. **match tag** *tag-name*
10. **end**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2	configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3	policy-map type control tag <i>policy-map-name</i> Example: Router(config)# policy-map type control tag all_tag_cm_pm	Creates a control policy map and enters policy-map configuration mode.
Step 4	class type control tag <i>control-class-name</i> Example: Router(config-pmap)# class type control tag auth_proxy_tag_cm	Creates a control class and enters policy-map-class configuration mode.
Step 5	identity policy <i>policy-name</i> Example: Router(config-pmap-c)# identity policy auth_proxy_ip	Creates an identity policy.
Step 6	exit Example: Router(config-pmap-c)# exit	Exits policy-map-class configuration mode.
Step 7	configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 8	class-map type control tag match-all <i>class-map-name</i> Example: Router(config)# class-map type control tag match-all auth_proxy_tag_cm	Creates a control class map and enters class-map configuration mode.

	Command or Action	Purpose
Step 9	match tag <i>tag-name</i> Example: Router(config-cmap)# match tag auth_proxy_tag	Specifies the tag to be matched for a tag type of class map.
Step 10	end Example: Router(config-cmap)# end	Exits class-map configuration mode.

Configuring Supplicant-Group Attribute on the ACS

The supplicant group attribute needs to be configured as a Cisco attribute value (AV) Pair on the ACS for user-based firewall support. To configure the supplicant-group attribute on the ACS, perform the steps in this section. The supplicant-group attribute is defined in the RADIUS and Lightweight Directory Access Protocol (LDAP) authorization group attributes from where all authorization data pertaining to the client resides. The user-group information is obtained from the ACS and no further user-group specific configuration is required on the NAD.

Cisco:Avpair=supplicant-group=eng

Defines the supplicant-group attribute.

Configuring Firewall Class-Maps and Policy-Maps

Perform the following task to configure firewall class-maps and policy-maps. User-groups are configured and attached to policy-maps by using the **inspect** command with each class-map.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **class-map type inspect match-all** *class-map-name*
4. **match protocol** *protocol-name*
5. **match user-group** *group-name*
6. **exit**
7. **configure terminal**
8. **policy-map type inspect** *policy-map-name*
9. **class type inspect** *class-map-name*
10. **inspect**
11. **end**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2	configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3	class-map type inspect match-all class-map-name Example: Router(config)# class-map type inspect match-all auth_proxy_ins_cm	Creates an inspect type class map and enters class-map configuration mode.
Step 4	match protocol protocol-name Example: Router(config-cmap)# match protocol telnet	Configures the match criterion for the class map on the basis of the specified protocol.
Step 5	match user-group group-name Example: Router(config-cmap)# match user-group auth_proxy_ug	Configures the match criterion for the class map on the basis of the specified user-group.
Step 6	exit Example: Router(config-cmap)# exit	Exits class-map configuration mode.
Step 7	configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 8	policy-map type inspect policy-map-name Example: Router(config)# policy-map type inspect all_ins_cm_pm	Creates an inspect type policy map and enters policy-map configuration mode.

	Command or Action	Purpose
Step 9	class type inspect <i>class-map-name</i> Example: <pre>Router(config-pmap)# class type inspect auth_proxy_ins_cm</pre>	Specifies the traffic (class) on which an action is to be performed.
Step 10	inspect Example: <pre>Router(config-pmap)# inspect</pre>	Enables Cisco IOS stateful packet inspection.
Step 11	end Example: <pre>Router(config-pmap)# end</pre>	Exits policy-map configuration mode.

Configuring Firewall Zone Security and Zone-Pair

To configure firewall zone security and zone -pair, perform the steps in this section. Security zones are configured for untrustworthy (outside) and trustworthy (inside) networks or interfaces. Zone-pairs are configured where the source zone is untrustworthy and the destination zone is trustworthy.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **zone security** *zone-name*
4. **end**
5. **configure terminal**
6. **zone-pair security** *zone-pair-name* **source** *source-zone-name* **destination** *destination-zone-name*
7. **service-policy type inspect** *policy-map-name*
8. **end**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable	Enables privileged EXEC mode.

	Command or Action	Purpose
	<p>Example:</p> <pre>Router> enable</pre>	<ul style="list-style-type: none"> Enter your password if prompted.
Step 2	<p>configure terminal</p> <p>Example:</p> <pre>Router# configure terminal</pre>	Enters global configuration mode.
Step 3	<p>zone security zone-name</p> <p>Example:</p> <pre>Router(config)# zone security out_sec_zone</pre>	Creates a security zone, and enters security zone configuration mode.
Step 4	<p>end</p> <p>Example:</p> <pre>Router(config-sec-zone)# end</pre>	Exits security zone configuration mode.
Step 5	<p>configure terminal</p> <p>Example:</p> <pre>Router# configure terminal</pre>	Enters global configuration mode.
Step 6	<p>zone-pair security zone-pair-name source source-zone-name destination destination-zone-name</p> <p>Example:</p> <pre>Router(config)# zone-pair security out_in source out_sec_zone destination in_sec_zone</pre>	Creates a zone-pair and enters security zone-pair configuration mode.
Step 7	<p>service-policy type inspect policy-map-name</p> <p>Example:</p> <pre>Router(config-sec-zone-pair)# service-policy type inspect all_ins_cm_pm</pre>	Attaches a firewall policy map to the zone-pair.
Step 8	<p>end</p> <p>Example:</p> <pre>Router(config-sec-zone-pair)# end</pre>	Exits security zone-pair configuration mode.

Configuring ACLs for Authentication Proxy

To configure ACLs for authentication proxy, perform the steps in this section.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **ip access-list extended** *access-list-name*
4. **permit** *protocol* **any** *source-ip-address* *destination-ip-address*
5. **permit** *protocol* **any host** *destination-ip-address*
6. **permit** *protocol* **any any eq bootps**
7. **permit** *protocol* **any any eq domain**
8. **end**
9. **configure terminal**
10. **ip access-list extended** *access-list-name*
11. **permit** *protocol* **any host** *destination-ip-address*
12. **permit** *protocol* **any host** *destination-ip-address* **eq domain**
13. **permit** *protocol* **any host** *destination-ip-address* **eq www**
14. **permit** *protocol* **any host** *destination-ip-address* **eq port**
15. **end**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2	configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3	ip access-list extended <i>access-list-name</i> Example: Router(config)# ip access-list extended 102	Defines an IP access list and enters extended named access list configuration mode.
Step 4	permit <i>protocol</i> any <i>source-ip-address</i> <i>destination-ip-address</i>	Sets the permission for an access list using IP.

	Command or Action	Purpose
	<p>Example:</p> <pre>Router(config-ext-nacl)# permit ip any 192.168.100.0 10.0.0.255</pre>	
Step 5	<p>permit protocol any host destination-ip-address</p> <p>Example:</p> <pre>Router(config-ext-nacl)# permit ip any host 192.168.104.136</pre>	Sets the permission for an access list using IP.
Step 6	<p>permit protocol any any eq bootps</p> <p>Example:</p> <pre>Router(config-ext-nacl)# permit ip any any eq bootps</pre>	Sets the permission for an access list using IP.
Step 7	<p>permit protocol any any eq domain</p> <p>Example:</p> <pre>Router(config-ext-nacl)# permit ip any any eq domain</pre>	Sets the permission for an access list using IP.
Step 8	<p>end</p> <p>Example:</p> <pre>Router(config-ext-nacl)# end</pre>	Exits extended named access list configuration mode.
Step 9	<p>configure terminal</p> <p>Example:</p> <pre>Router# configure terminal</pre>	Enters global configuration mode.
Step 10	<p>ip access-list extended access-list-name</p> <p>Example:</p> <pre>Router(config)# ip access-list extended 103</pre>	Defines an IP access list and enters extended named access list configuration mode.
Step 11	<p>permit protocol any host destination-ip-address</p> <p>Example:</p> <pre>Router(config-ext-nacl)# permit ip any host 192.168.104.136</pre>	Sets the permission for an access list using IP.

	Command or Action	Purpose
Step 12	<pre>permit protocol any host destination-ip-address eq domain</pre> <p>Example:</p> <pre>Router(config-ext-nacl)# permit udp any host 192.168.104.136 eq domain</pre>	Sets the permission for an access list using user datagram protocol (UDP).
Step 13	<pre>permit protocol any host destination-ip-address eq www</pre> <p>Example:</p> <pre>Router(config-ext-nacl)# permit tcp any host 192.168.104.136 eq www</pre>	Sets the permission for an access list using TCP.
Step 14	<pre>permit protocol any host destination-ip-address eq port</pre> <p>Example:</p> <pre>Router(config-ext-nacl)# permit udp any host 192.168.104.136 eq 443</pre>	Sets the permission for an access list using UDP.
Step 15	<pre>end</pre> <p>Example:</p> <pre>Router(config-ext-nacl)# end</pre>	Exits extended named access list configuration mode.

Configuring Authentication Proxy

To configure authentication proxy default IP admissions, perform the steps in this task.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **ip admission auth-proxy-banner http c Auth-Proxy-Banner-Text c**
4. **ip admission watch-list expiry-time expiry-minutes**
5. **ip admission max-login-attempts attempt-number**
6. **ip admission inactivity-timer timeout-minutes**
7. **ip admission absolute-timer timeout-minutes**
8. **ip admission init-state-timer timeout-minutes**
9. **ip admission auth-proxy-audit**
10. **ip admission watch-list enable**
11. **ip admission ratelimit limit**
12. **ip admission name admission-name proxy http list acl**
13. **ip admission name admission-name proxy telnet list acl**
14. **ip admission name admission-name proxy http list acl service-policy type tag service-policy-name**
15. **exit**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2	configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3	ip admission auth-proxy-banner http c Auth-Proxy-Banner-Text c Example: Router(config)# ip admission auth-proxy-banner http c Auth-Proxy-Banner-Text c	Creates a network admission control rule with an authentication proxy banner to be applied to the interface.
Step 4	ip admission watch-list expiry-time expiry-minutes Example: Router(config)# ip admission watch-list expiry-time 50	Creates a network admission control rule with a watch-list to be applied to the interface.

	Command or Action	Purpose
Step 5	<p>ip admission max-login-attempts <i>attempt-number</i></p> <p>Example:</p> <pre>Router(config)# ip admission max-login-attempts 10</pre>	Creates a network admission control rule with a specified maximum login attempts per user number to be applied to the interface.
Step 6	<p>ip admission inactivity-timer <i>timeout-minutes</i></p> <p>Example:</p> <pre>Router(config)# ip admission inactivity-timer 205</pre>	Creates a network admission control rule with a specified inactivity timeout to be applied to the interface.
Step 7	<p>ip admission absolute-timer <i>timeout-minutes</i></p> <p>Example:</p> <pre>Router(config)# ip admission absolute-timer 305</pre>	Creates a network admission control rule with a specified absolute timeout to be applied to the interface.
Step 8	<p>ip admission init-state-timer <i>timeout-minutes</i></p> <p>Example:</p> <pre>Router(config)# ip admission init-state-timer 15</pre>	Creates a network admission control rule with a specified init-state timeout to be applied to the interface.
Step 9	<p>ip admission auth-proxy-audit</p> <p>Example:</p> <pre>Router(config)# ip admission auth-proxy-audit</pre>	Creates a network admission control rule with authentication proxy auditing to be applied to the interface.
Step 10	<p>ip admission watch-list enable</p> <p>Example:</p> <pre>Router(config)# ip admission watch-list enable</pre>	Creates a network admission control rule with a watch-list to be applied to the interface.
Step 11	<p>ip admission ratelimit <i>limit</i></p> <p>Example:</p> <pre>Router(config)# ip admission ratelimit 100</pre>	Creates a network admission control rule with a specified session rate limit to be applied to the interface.
Step 12	<p>ip admission name <i>admission-name</i> proxy http list <i>acl</i></p> <p>Example:</p> <pre>Router(config)# ip admission name auth_rule proxy http list 103</pre>	<p>Creates an IP network admission control rule.</p> <ul style="list-style-type: none"> • Telnet, HTTP, or both can be configured.

	Command or Action	Purpose
Step 13	<p>ip admission name <i>admission-name</i> proxy telnet list <i>acl</i></p> <p>Example:</p> <pre>Router(config)# ip admission name auth_rule proxy telnet list 103</pre>	<p>Creates an IP network admission control rule.</p> <ul style="list-style-type: none"> Telnet, HTTP, or both can be configured.
Step 14	<p>ip admission name <i>admission-name</i> proxy http list <i>acl</i> service-policy type tag <i>service-policy-name</i></p> <p>Example:</p> <pre>Router(config)# ip admission name auth_rule proxy http list 103 service-policy type tag all_tag_cm_pm</pre>	<p>(Optional) Creates an IP network admission control rule.</p> <ul style="list-style-type: none"> Configures a control plane service policy when the Tag & Template method of user-group association is used. Control plane tag service policy that is configured using the policy-map type control tag <i>policy name</i> command, keyword, and argument. This policy map is used to apply the actions on the host when a tag is received.
Step 15	<p>exit</p> <p>Example:</p> <pre>Router(config)# exit</pre>	<p>Exits global configuration mode.</p>

Configuring AAA and RADIUS

To configure AAA and RADIUS servers, perform the steps in this task.

SUMMARY STEPS

1. enable
2. configure terminal
3. aaa new-model
4. aaa authentication login default group radius
5. aaa authentication login *list-name* none
6. aaa authentication eou default enable group radius
7. aaa authorization network default group radius local
8. aaa authorization *list-name* default group radius
9. aaa accounting auth-proxy default start-stop group *group-name*
10. aaa accounting system default start-stop group *group-name*
11. aaa session-id common
12. radius-server attribute 6 on-for-login-auth
13. radius-server attribute 8 include-in-access-req
14. radius-server attribute 25 access-request include
15. radius-server configure-nas
16. radius-server host *ip-address* auth-port *port-number* acct-port *port-number* key *string*
17. radius-server host *ip-address* auth-port *port-number* acct-port *port-number* key *string*
18. radius-server source-ports extended
19. radius-server vsa send authentication
20. exit

DETAILED STEPS

	Command or Action	Purpose
Step 1	<p>enable</p> <p>Example:</p> <pre>Router> enable</pre>	<p>Enables privileged EXEC mode.</p> <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2	<p>configure terminal</p> <p>Example:</p> <pre>Router# configure terminal</pre>	<p>Enters global configuration mode.</p>
Step 3	<p>aaa new-model</p> <p>Example:</p> <pre>Router(config)# aaa new-model</pre>	<p>Enables the AAA access control model.</p>

	Command or Action	Purpose
Step 4	aaa authentication login default group radius Example: <pre>Router(config)# aaa authentication login default group radius</pre>	Sets AAA authentication at login using the group radius method.
Step 5	aaa authentication login list-name none Example: <pre>Router(config)# aaa authentication login noAAA none</pre>	Sets AAA authentication at login and ensures that the authentication succeeds even if all methods of authentication return an error.
Step 6	aaa authentication eou default enable group radius Example: <pre>Router(config)# aaa authentication eou default enable group radius</pre>	Sets authentication lists for Extensible Authentication Protocol over User Datagram Protocol (EAPoUDP).
Step 7	aaa authorization network default group radius local Example: <pre>Router(config)# aaa authorization network default group radius local</pre>	Sets parameters that restrict user access to a network using the group radius and local methods. <ul style="list-style-type: none"> • The group radius method uses the list of all RADIUS servers for authentication. • The local method uses the local database for authorization.
Step 8	aaa authorization list-name default group radius Example: <pre>Router(config)# aaa authorization auth-proxy default group radius</pre>	Sets parameters that restrict user access to a network using the group radius method.
Step 9	aaa accounting auth-proxy default start-stop group group-name Example: <pre>Router(config)# aaa accounting auth-proxy default start-stop group radius</pre>	Creates a method list to provide information about all authenticated-proxy user events. <ul style="list-style-type: none"> • Sends a “start” accounting notice at the beginning of a process and a “stop” accounting notice at the end of a process.
Step 10	aaa accounting system default start-stop group group-name Example: <pre>Router(config)# aaa accounting system default start-stop group radius</pre>	Creates a method list to provide accounting for all system-level events not associated with users. <ul style="list-style-type: none"> • Sends a “start” accounting notice at the beginning of a process and a “stop” accounting notice at the end of a process.

	Command or Action	Purpose
Step 11	aaa session-id common Example: Router(config)# aaa session-id common	Specifies that the same ID will be assigned for each AAA accounting service type within a call.
Step 12	radius-server attribute 6 on-for-login-auth Example: Router(config)# radius-server attribute 6 on-for-login-auth	Sends the Service-Type attribute in the authentication packets.
Step 13	radius-server attribute 8 include-in-access-req Example: Router(config)# radius-server attribute 8 include-in-access-req	Sends the IP address of a user to the RADIUS server in the access request.
Step 14	radius-server attribute 25 access-request include Example: Router(config)# radius-server attribute 25 access-request include	Sends an arbitrary value that the network access server includes in all accounting packets for the user if supplied by the RADIUS server.
Step 15	radius-server configure-nas Example: Router(config)# radius-server configure-nas	Configures the Cisco router or access server to query the vendor-proprietary RADIUS server for the static routes and IP pool definitions used throughout its domain when the device starts up.
Step 16	radius-server host ip-address auth-port port-number acct-port port-number key string Example: Router(config)# radius-server host 192.168.104.131 auth-port 1645 acct-port 1646 key string1	Specifies a RADIUS server host. <ul style="list-style-type: none"> • Specifies the UDP destination port for authentication requests. • Specifies the UDP destination port for accounting requests.
Step 17	radius-server host ip-address auth-port port-number acct-port port-number key string Example: Router(config)# radius-server host 192.168.104.132 auth-port 1645 acct-port 1646 key string2	Specifies a RADIUS server host. <ul style="list-style-type: none"> • Specifies the UDP destination port for authentication requests. • Specifies the UDP destination port for accounting requests.

	Command or Action	Purpose
Step 18	radius-server source-ports extended Example: <pre>Router(config)# radius-server source-ports extended</pre>	Enables 200 ports in the range from 21645 to 21844 to be used as the source ports for sending out RADIUS requests. <ul style="list-style-type: none"> • Ports 1645 and 1646 are used as the source ports for RADIUS requests.
Step 19	radius-server vsa send authentication Example: <pre>Router(config)# radius-server vsa send authentication</pre>	Configures the network access server (NAS) to recognize and use vendor-specific attributes (VSAs).
Step 20	exit Example: <pre>Router(config)# exit</pre>	Exits global configuration mode.

Configuring AAA and LDAP

Perform this task to configure AAA and LDAP servers:

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **aaa new-model**
4. **aaa authentication login default group ldap**
5. **aaa authentication login list-name none**
6. **aaa authorization network default group ldap local**
7. **aaa authorization list-name default group ldap**
8. **ldap attribute map map-name**
9. **map type ldap-attr-type aaa-attr-type**
10. **exit**
11. **ldap server name**
12. **ipv4 ipv4-address**
13. **bind authenticate root-dn username password [0 string | 7 string] string**
14. **base-dn string**
15. **attribute map map-name**
16. **exit**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: <pre>Router> enable</pre>	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2	configure terminal Example: <pre>Router# configure terminal</pre>	Enters global configuration mode.
Step 3	aaa new-model Example: <pre>Router(config)# aaa new-model</pre>	Enables the AAA access control model.
Step 4	aaa authentication login default group ldap Example: <pre>Router(config)# aaa authentication login default group ldap</pre>	Sets AAA authentication at login using the group LDAP method.
Step 5	aaa authentication login list-name none Example: <pre>Router(config)# aaa authentication login AAA none</pre>	Sets AAA authentication at login and ensures that the authentication succeeds even if all methods of authentication return an error.
Step 6	aaa authorization network default group ldap local Example: <pre>Router(config)# aaa authorization network default group ldap local</pre>	Sets parameters that restrict user access to a network using the group LDAP and local methods. <ul style="list-style-type: none"> • The group LDAP method uses the list of all LDAP servers for authentication. • The local method uses the local database for authorization.
Step 7	aaa authorization list-name default group ldap Example: <pre>Router(config)# aaa authorization auth-proxy default group ldap</pre>	Sets parameters that restrict user access to a network using the group LDAP method.

	Command or Action	Purpose
Step 8	<p>ldap attribute map <i>map-name</i></p> <p>Example:</p> <pre>Router(config)# ldap attribute map map1</pre>	Configures dynamic LDAP attribute map and enters attribute-map configuration mode.
Step 9	<p>map type <i>ldap-attr-type aaa-attr-type</i></p> <p>Example:</p> <pre>Router(config-attr-map)# map type supp-grp supplicant-group</pre>	Defines an attribute map.
Step 10	<p>exit</p> <p>Example:</p> <pre>Router(config-attr-map)# exit</pre>	Exits the attribute-map configuration mode.
Step 11	<p>ldap server <i>name</i></p> <p>Example:</p> <pre>Router(config)# ldap server ldap_dir_1</pre>	Specifies the LDAP server name and enters LDAP server configuration mode.
Step 12	<p>ipv4 <i>ipv4-address</i></p> <p>Example:</p> <pre>Router(config-ldap-server)# ipv4 10.0.0.1</pre>	Specifies the IP address of the LDAP server.
Step 13	<p>bind authenticate root-dn <i>username password [0 string 7 string] string</i></p> <p>Example:</p> <pre>Router(config-ldap-server)# bind authenticate root-dn "cn=adminstrator,cn=users, dc=cisco,dc=com password"</pre>	Authenticates a client to a LDAP server.
Step 14	<p>base-dn <i>string</i></p> <p>Example:</p> <pre>Router(config-ldap-server)# base-dn dc=example,dc=sns,dc=com</pre>	(Optional) Configures the base DN that you want to use to perform search operations in the LDAP directory tree.
Step 15	<p>attribute map <i>map-name</i></p> <p>Example:</p> <pre>Router(config-ldap-server)# attribute map map1</pre>	Attaches the attribute map to a particular LDAP server.

	Command or Action	Purpose
Step 16	exit Example: Router(config-ldap-server)# exit	Exits LDAP server group configuration mode.

Troubleshooting Tips

The following commands can be used to troubleshoot User-Based Firewall Support:

- **clear ip admission cache**
- **debug user-group**
- **show debugging**
- **show epm session ip**
- **show ip access-lists**
- **show ip admission**
- **show logging**
- **show policy-map type inspect zone-pair**
- **show user-group**

Examples

show epm session ip

The following example shows sample output of the **show epm session** command when the **summary** keyword is used.

```
Router# show epm session ip summary
EPM Session Information
-----
Total sessions seen so far: 8
Total Active sessions: 1
Session IP Address:
-----
192.168.101.131
```

The following example shows sample output of the **show epm session** command when the *ip-address* argument is specified. The output below is displayed if a locally defined user-group association (Tag and Template method) is used.

```
Router# show epm session ip 192.168.101.131
Admission feature: Authproxy
Tag Received: eng_group_tag
Policy map used: all_tag_cm_pm
Class map matched: eng_tag_cm
```

The following example shows sample output of the **show epm session** command when the *ip-address* argument is specified. The output below is displayed if ACS defined (supplicant-group attribute configured on the ACS) user-group association is used.

```
Router# show epm session ip 192.168.101.131
Admission feature: Authproxy
AAA policies:
ACS ACL: xACSACLx-IP-TEST_ACL-47dfc392
Supplicant-Group: eng
Supplicant-Group: mgr
Proxy ACL: permit udp any any
Router#
```

show ip access-lists

The following example shows sample output of the **show ip access-lists** command.

```
Router# show ip access-lists
Extended IP access list 102
 permit icmp host 192.168.101.131 host 192.168.104.136 Auth-Proxy ACE downloaded from AAA
 permit udp host 192.168.101.131 host 192.168.104.136 Auth-Proxy ACE downloaded from AAA
 permit tcp host 192.168.101.131 host 192.168.104.136 Auth-Proxy ACE downloaded from AAA
10 permit ip any 192.168.100.0 10.0.0.255 (956 matches)
20 permit ip any 192.168.101.0 10.0.0.255 (9 matches)
30 permit ip any host 192.168.104.136 (20 matches)
40 permit udp any any eq bootps
50 permit udp any any eq domain
Extended IP access list 103

10 permit ip any host 192.168.104.136 (3 matches)
20 permit udp any host 192.168.104.136 eq domain
30 permit tcp any host 192.168.104.136 eq www
40 permit udp any host 192.168.104.136 eq 443
50 permit tcp any host 192.168.104.136 eq 443
Extended IP access list vendor_group_acl
10 permit ip any host 192.168.104.136
Extended IP access list auth_proxy_acl
10 permit tcp any host 192.168.104.136
20 permit udp any host 192.168.104.136
30 permit icmp any host 192.168.104.136
Extended IP access list sales_group_acl
10 permit ip any host 192.168.104.131
Extended IP access list eng_group_acl
10 permit ip any host 192.168.100.132
Extended IP access list manager_group_acl
10 permit ip any host 192.168.104.128
Router#
```

show ip admission

The following is sample output of the **show ip admission** command when the **configuration** keyword is used.

```
Router# show ip admission configuration
Authentication Proxy Banner
 HTTP Protocol Banner: Auth-Proxy-Banner-Text
Authentication global cache time is 205 minutes
Authentication global absolute time is 305 minutes
Authentication global init state time is 15 minutes
Authentication Proxy Session ratelimit is 100
Authentication Proxy Session Watch-list is enabled
Watch-list expiry timeout is 50 minutes
Authentication Proxy Auditing is enabled
Max Login attempts per user is 10
Authentication Proxy Rule Configuration
Auth-proxy name auth_rule
```

```

http list 103 inactivity-timer 205 minutes
Router#

```

The following is sample output of the **show ip admission** command when the **cache** keyword is used. After a successful Telnet/HTTP-proxy session, from a Cisco Trust Agent (CTA) client to an Audit Server, is established, logs are displayed.

```

Router# show ip admission cache
Authentication Proxy Cache
Client Name aaatestuser, Client IP 192.168.101.131, Port 1870, timeout 205, Time Remaining
205, state ESTAB

```

show logging

The following is sample output of the **show logging** command.

```

Router# show logging
Log Buffer (65000 bytes):
*Jul 3 05:33:13.935: %SYS-5-CONFIG_I: Configured from console by console
*Jul 3 05:33:18.471: USRGRP-API: [Type=IPv4 Val=192.168.101.131 Group=h_ug]: Usergroup
opcode entry deletion.
*Jul 3 05:33:18.471: %UG-6-MEMBERSHIP: IP=192.168.101.131| INTERFACE=Vlan|
USERGROUP=eng_group_ug| STATUS=REMOVED
*Jul 3 05:33:18.471: USRGRP-ENTRY: [Type=IPv4 Val=192.168.101.131 :: Group=eng_group_ug
Count=0]:Usergroup entry deleted
*Jul 3 05:33:18.471: USRGRP-ENTRY: [Type=IPv4 Val=192.168.101.131 :: Group=eng_group_ug
Count=0]:Usergroup entry clean up and free
*Jul 3 05:33:18.471: USRGRP-DB: Group=h_ug Count=0: Usergroup is empty. Destroy Group.
*Jul 3 05:33:18.471: USRGRP-DB: Group=h_ug Count=0: Clean up and free usergroup db.
*Jul 3 05:33:22.383: USRGRP-API: [Type=IPv4 Val=192.168.101.131 Group=eng_group_ug]: Usergroup
opcode entry addition.
*Jul 3 05:33:22.383: USRGRP-DB: Group=h_ug Count=0 New usergroup db created.
*Jul 3 05:33:22.383: %UG-6-MEMBERSHIP: IP=192.168.101.131| INTERFACE=Vlan333|
USERGROUP=eng_group_ug| STATUS=ESTABLISHED
*Jul 3 05:33:22.383: USRGRP-ENTRY: [Type=IPv4 Val=192.168.101.131 :: Group=eng_group_ug
Count=1]: Usergroup entry added
*Jul 3 05:33:41.239: USRGRP-API: [Type=IPv4 Val=192.168.101.131 Group=eng_group_ug]: Usergroup
opcode entry deletion.
*Jul 3 05:33:41.239: %UG-6-MEMBERSHIP: IP=192.168.101.131| INTERFACE=Vlan333|
USERGROUP=eng_group_ug| STATUS=REMOVED
*Jul 3 05:33:41.239: USRGRP-ENTRY: [Type=IPv4 Val=192.168.101.131 :: Group=eng_group_ug
Count=0]: Usergroup entry deleted
*Jul 3 05:33:41.239: USRGRP-ENTRY: [Type=IPv4 Val=192.168.101.131 :: Group=eng_group_ug
Count=0]: Usergroup entry clean up and free
*Jul 3 05:33:41.239: USRGRP-DB: Group=eng_group_ug Count=0: Usergroup is empty. Destroy
group.
*Jul 3 05:33:41.239: USRGRP-DB: Group=eng_group_ug Count=0: Clean up and free usergroup db.
*Jul 3 05:33:50.687: USRGRP-API: {Type=IPv4 Val=192.168.101.131 Group=eng_group_ug}: Usergroup
opcode entry addition.
*Jul 3 05:33:50.687: USRGRP-DB: Group=eng_group_ug Count=0: New usergroup db created.
*Jul 3 05:33:50.687: %UG-6-MEMBERSHIP: IP=192.168.101.131| INTERFACE=Vlan333|
USERGROUP=eng_group_ug| STATUS=ESTABLISHED
*Jul 3 05:33:50.687: USRGRP-ENTRY: [Type=IPv4 Val=192.168.101.131 :: Group=eng_group_ug
Count=1]: Usergroup entry added

```

show policy-map type inspect zone-pair

The following is sample output of the **show policy-map type inspect zone-pair** command when the **sessions** keyword is used.

```

Router# show policy-map type inspect zone-pair sessions
policy exists on zp out_in
Zone-pair: out_in
Service-policy inspect: all_ins_cm_pm
Class-map: vendor_group_ins_cm (match-all)
Match: user-group vendor_group_ug
Class-map: manager_group_ins_cm (match-all)
Match: protocol telnet

```

```

Match: user-group manager_group_ug
Class-map: auth_proxy_ins_cm (match-all)
Match: user-group auth_proxy_ug
Match: protocol telnet
Number of Established Sessions = 1
Established Sessions
  Session 49D12BE0 (192.168.101.131:1872)=>(192.168.104.136:23) telnet:tcp SIS_OPEN
    Created 00:00:15, Last heard 00:00:09
    Bytes sent (initiator:responder) [171:249]
Class-map: eng_group_ins_cm (match-all)
Match: user-group eng_group_ug
Match: protocol ftp
Number of Established Sessions = 1
Established Sessions
  Session 49D12E20 (192.168.101.131:1874)=>(192.168.104.136:21) ftp:tcp SIS_OPEN
    Created 00:00:12, Last heard 00:00:06
    Bytes sent (initiator:responder) [45:137]
Class-map: sales_group_ins_cm (match-all)
Match: protocol ftp
Match: user-group sales_group_ug
Class-map: class-default (match-any)
Match: any

```

show user-group

The following is sample output of the **show user-group** command when the **configuration** keyword is used.

```

Router# show user-group
Usergroup: auth_proxy_ug
-----
User Name      Type  Interface  Learn  Age (min)
-----
192.168.101.131 IPv4    Vlan333   Dynamic  0
Usergroup: eng_group_ug
-----
User Name      Type  Interface  Learn  Age (min)
-----
192.168.101.131 IPv4    Vlan333   Dynamic  0

```

The following is sample output of the **show user-group** command when the *group-name* argument is used.

```

Router# show user-group auth_proxy_ug
Usergroup: auth_proxy_ug
-----
User Name      Type  Interface  Learn  Age (min)
-----
192.168.101.131 IPv4    Vlan333   Dynamic  0

```

The following is sample output of the **show user-group** command when the **count** keyword is used.

```

Router# show user-group count
Total Usergroup: 2
-----
User Group      Members
-----
auth_proxy_ug   1
eng_proxy_ug    1

```

Configuration Examples for User-Based Firewall Support

Cisco IOS Authentication Proxy Example

The following example shows how to configure User-Based Firewall Support. The Cisco IOS Authentication Proxy maps two users to different user-groups. Zone Policy Firewall policies are configured on a per user-group basis.

```

!IP Admission configuration
Configure the rule for HTTP based proxy authentication and associate the control plane tag
service policy.
!
configure terminal
ip admission name auth-http proxy http service-policy type tag global-policy
ip http server
ip http secure-server
!AAA configuration
!
aaa new-model
!
aaa authentication login default group radius
aaa authentication login noAAA none
aaa authentication eou default group radius
aaa authorization network default group radius local
aaa authorization auth-proxy default group radius
aaa accounting auth-proxy default start-stop group radius
aaa accounting system default start-stop group radius
aaa session-id common
!
radius-server attribute 6 on-for-login-auth
radius-server attribute 8 include-in-access-req
radius-server attribute 25 access-request include
radius-server configure-nas
radius-server host 192.168.104.131 auth-port 1645 acct-port 1646 key cisco
radius-server host 192.168.104.132 auth-port 1645 acct-port 1646 key cisco
radius-server source-ports extended
radius-server vsa send authentication
!
!Tag and Template configuration.
Configuration policy attributes for the engineer.
!
identity policy engineer-policy
access-group engineer-acl
user-group group-engineer
identity policy manager-policy
access-group manager-acl
user-group group-manager
!Define type control tag class-maps
!
class-map type control tag match-all auth_proxy_tag_cm
match tag auth_proxy_tag
class-map type control tag match-all eng_tag_cm
match tag eng_group_tag
class-map type control tag match-all manager_tag_cm
match tag manager_group_tag
!
!Define the control plane tag policy map.
!
policy-map type tag control tag global-policy
class engineer-class
identity policy engineer-policy
class manager-class
identity policy manager-policy
!Define per-user group traffic classification based on membership of the source IP address
in the specified user-group.

```

```

!
class-map type inspect match-all engineer-insp-cmap
  match user-group group-engineer
  match protocol tcp
  match protocol udp
class-map type inspect match-all manager-insp-cmap
  match user-group group-manager
  match protocol http
!Zone Policy Firewall configuration.
Configure zones z1 and z2.
!
zone security z1
zone security z2
!Configure the policy map to inspect traffic between z1 and z2.
!
policy-map type inspect z1-z2-policy
  class type inspect engineer-insp-cmap
    inspect
  class type inspect manager-insp-cmap
    inspect
!Configure interfaces to their respective zones and apply the ip admission rule on the
source zone member(s).
!
interface e0
  ip admission auth-http
  zone-member security z1
interface e1
  zone-member security z2
!Configure the zone-pair and apply the appropriate policy-map.
!
zone-pair security z1-z2 source z1 destination z2
  service-policy type inspect z1-z2-policy

```

Additional References

The following sections provide references related to the User-Based Firewall Support feature.

Related Documents

Related Topic	Document Title
Cisco IOS Firewall Design	The Cisco IOS Firewall Design Guide
Cisco IOS firewall commands	<i>Cisco IOS Security Command Reference</i>
Cisco IOS Tag and Template	“Tag and Template” module
Cisco IOS Zone-Based Policy Firewall	Zone-Based Policy Firewall” module
Cisco IOS Authentication Proxy	“Authentication Proxy” module

Standards

Standard	Title
No new or modified standards are supported by this feature, and support for existing standards has not been modified by this feature.	--

MIBs

MIB	MIBs Link
None	To locate and download MIBs for selected platforms, Cisco IOS releases, and feature sets, use Cisco MIB Locator found at the following URL: http://www.cisco.com/go/mibs

RFCs

RFC	Title
None	--

Technical Assistance

Description	Link
<p>The Cisco Support website provides extensive online resources, including documentation and tools for troubleshooting and resolving technical issues with Cisco products and technologies.</p> <p>To receive security and technical information about your products, you can subscribe to various services, such as the Product Alert Tool (accessed from Field Notices), the Cisco Technical Services Newsletter, and Really Simple Syndication (RSS) Feeds.</p> <p>Access to most tools on the Cisco Support website requires a Cisco.com user ID and password.</p>	http://www.cisco.com/cisco/web/support/index.html

Feature Information for User-Based Firewall Support

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Table 1: Feature Information for User-Based Firewall Support

Feature Name	Releases	Feature Information
User-Based Firewall Support	12.4(20)T	<p>This feature provides the option for configuring a security solution to dynamically authenticate and enforce policies on a per user basis in Cisco IOS software for Release 12.4(20)T and later releases.</p> <p>In Release 12.4(20)T, this feature was introduced on the Cisco 7200, Cisco 1800, Cisco 2800, and Cisco 3800 routers.</p> <p>The following commands were introduced or modified: debug user-group, match user-group, show debugging, show user-group, user-group, user-group logging.</p>
LDAP Active Directory support for authproxy	15.1(1)T	<p>This feature enables the authentication proxy to authenticate and authorize the users with the Active Directory server using LDAP.</p> <p>The following commands were introduced or modified: aaa authentication, aaa authorization, attribute map, bind authenticate, base-dn, ipv4, ldap attribute map, map type, ldap server.</p>